Package: fireexposuR (via r-universe)

March 24, 2025

```
Type Package
Title Compute and Visualize Wildfire Exposure
Version 1.1.0
Description This package computes and visualizes wildfire exposure
     using the methods documented in a series of scientific
     publications.
License GPL (>= 3)
Imports dplyr, geosphere, ggplot2, ggspatial, magrittr, maptiles,
     MultiscaleDTM, rlang, terra, tidyr, tidyselect, tidyterra
Encoding UTF-8
LazyData true
RoxygenNote 7.3.2
Roxygen list(markdown = TRUE)
URL https://github.com/ropensci/fireexposuR,
     https://docs.ropensci.org/fireexposuR/
BugReports https://github.com/ropensci/fireexposuR/issues
Suggests knitr, rmarkdown, testthat (>= 3.0.0)
Config/testthat/edition 3
Depends R (>= 2.10)
VignetteBuilder knitr
Config/pak/sysreqs libfreetype6-dev libgdal-dev gdal-bin libgeos-dev
     libglu1-mesa-dev make libicu-dev libjpeg-dev libpng-dev
     libgl1-mesa-dev libssl-dev libsroj-dev libsqlite3-dev
     libudunits2-dev zlib1g-dev
Repository https://ropensci.r-universe.dev
RemoteUrl https://github.com/ropensci/fireexposuR
RemoteRef main
RemoteSha 31035c9bb261505a9873fbf4b10b20c30a6514c8
```

2 fire_exp

Contents

fire_exp	2
fire_exp_adjust	5
fire_exp_dir	6
fire_exp_dir_map	9
fire_exp_dir_multi	10
fire_exp_dir_plot	12
fire_exp_extract	13
fire_exp_extract_vis	14
fire_exp_map_class	17
fire_exp_map_cont	19
fire_exp_summary	20
fire_exp_validate	21
fire_exp_validate_plot	23
	25

fire_exp

Index

Compute the wildfire exposure metric

Description

fire_exp() returns a SpatRaster of wildfire exposure values calculated using the input hazard fuel raster for a specified transmission distance.

Usage

```
fire_exp(hazard, tdist = c("1", "s", "r"), no_burn)
```

Arguments

hazard	a SpatRaster that represents hazardous fuels for the transmission distance specified in tdist
tdist	a character vector, can be: "1" for long-range embers (Default), "s" for short-range embers or, "r" for radiant heat
no_burn	(optional) a SpatRaster that represents the non-burnable landscape. Any cells that cannot receive wildfire (e.g. open water, rock) and any cells that are not natural (e.g. built environment, irrigated agricultural areas) should be of value 1, all other cells should be NODATA. This parameter should be provided if preparing data for fire_exp_validate()

fire_exp 3

Details

This function is the primary function in this package, the output from this function serves as the first input to all other functions in this package.

Background:

Wildfire exposure was first proposed for community scale assessments by Beverly et al. (2010). Wildfire entry points to the built environment were identified by evaluating the surrounding wildland fuels as potential ignition sources. These methods were adapted and validated by Beverly et al. (2021) for landscape scale assessments. Visual aids to better understand these concepts are available in the Wildfire Exposure Assessment Guidebook (FireSmart Canada 2018) which includes intuitive illustrations.

Three transmission distances were defined in Beverly et al. (2010) for different scales of wildfire ignition processes. Different fuel types are capable of transmitting fire at different scales. The transmission distances define a potential maximum spread distance from an ignition source. If the default distances do not accurately represent fire behaviour in your area of interest you can adjust them with fire_exp_adjust().

Radiant heat:

The default transmission distance for radiant heat is 30 meters. At this scale of wildfire transmission wildfire can spread from direct flame contact or thermal radiation warming of fuels.

Ember spotting:

Embers (AKA firebrands) can be carried by wind beyond the active fire front. To determin two different ember spreading distances Beverly et al. (2010) reviewed fire-spot distance observations and applied predictive models to verify these distances were a reasonable assumption.

Short-range embers:

The default transmission distance for short-range embers is 100 meters. Some fuel types have the potential to produce embers over short distances. An example fuel type that has the potential to transmit short-range embers is a deciduous forest. Fuels considered hazardous to short-range ember ignition will also be hazardous to transmit fire via radiant heat or direct flame contact.

Long-range embers:

The default transmission distance for long-range embers is 500 meters. Some fuel types have the potential to transmit embers across large distances. This landscape scale process is often a contributor to large, fast-moving fires. Any fuels that are considered hazardous for long-range ember spotting could also transmit fire by short-range ember spotting and radiant heat. An example fuel type that has the potential to transmit long-range embers is a mature pine stand. Although it is possible for embers from certain fuel types to be carried much farther than the defined 500 meter transmission distance under extreme conditions, these cases are relatively uncommon.

The 500 meter spread distance has been further validated across Alberta (Beverly et al. 2021), in Alaska (Schmidt et al. 2024), across the entire Canadian landbase (manuscript in preparation), and in Portugal (manuscript in preparation).

Technical:

How the metric is calculated:

The wildfire exposure metric is calculated for each cell individually using a focal window of the surrounding cells within the specified transmission distance. The proportion of cells within the assessment window that are classed as hazardous is returned. The wildfire exposure metric 4 fire_exp

has a range of 0-1. A wildfire exposure value of 0.5 can be interpreted as 50% of cells within the specified transmission distance area have the potential to spread fire to the assessment cell. A value of 0.5 can also be interpreted in the other direction, a fire in the assessment cell could potentially spread to 50% of the surrounding cells within the specified transmission distance.

Input features:

An input hazard raster must be prepared by the user in accordance with the intended use. First, refer to the Get Started vignette by running vignette("fireexposuR") to determine what the data requirements are for the intended application. Then refer to the Preparing Input Data vignette by running vignette("prep-input-data") for lots of recommendations, advice, and examples.

A separate hazard raster should be prepared for each of the transmission distances of interest. There are also minimum spatial resolution and extent requirements for each transmission distances.

Long-range embers:

- minimum raster resolution is 150 meters
- The dimensions of the data must be wider/taller than 1000 meters because 500 meters of data will be lost along the perimeter due to edge effects

Short-range embers:

- minimum raster resolution is 33 meters
- The dimensions of the data must be wider/taller than 200 meters because 100 meters of data will be lost along the perimeter due to edge effects

Radiant heat:

- minimum raster resolution is 10 meters
- The dimensions of the data must be wider/taller than 60 meters because 30 meters of data will be lost along the perimeter due to edge effects

Spatial Reference:

The exposure raster will be returned in the same CRS as the input hazard layer. A crs must be defined if the outputs will be used in other functions in this package.

Value

A SpatRaster object of exposure values between 0-1

References

Beverly JL, McLoughlin N, Chapman E (2021) A simple metric of landscape fire exposure. *Landscape Ecology* **36**, 785-801. DOI

Beverly JL, Bothwell P, Conner JCR, Herd EPK (2010) Assessing the exposure of the built environment to potential ignition sources generated from vegetative fuel. *International Journal of Wildland Fire* **19**, 299-313. DOI

FireSmart Canada (2018) Wildfire exposure assessment guidebook. Available here

Hijmans R (2024). terra: Spatial Data Analysis. R package version 1.7-78, CRAN.

Schmidt JI, Ziel RH, Calef MP, Varvak A (2024) Spatial distribution of wildfire threat in the far north: exposure assessment in boreal communities. *Natural Hazards* **120**, 4901-4924. DOI

fire_exp_adjust 5

Examples

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))
# compute long range exposure
fire_exp(hazard, tdist = "l")</pre>
```

fire_exp_adjust

Compute the wildfire exposure metric with custom transmission dis-

tances

Description

For advanced users. Adjust the transmission distances from the defaults used in fire_exp().

Usage

```
fire_exp_adjust(hazard, tdist, no_burn)
```

Arguments

hazard a SpatRaster that represents hazardous fuels for the transmission distance spec-

ified in tdist

tdist Numeric, transmission distance in meters

no_burn (Optional) SpatRaster that represents the non-burnable landscape. Any cells that

cannot receive wildfire (e.g. open water, rock) and any cells that are not natural (e.g. built environment, irrigated agricultural areas) should be of value 1, all other cells should be NODATA. This parameter should be provided if preparing

data for fire_exp_validate()

Details

If the transmission distances from the wildfire exposure literature are not representative of the wildland fuels in your area of interest, this function can be used to change the transmission distance to a custom distance. It is highly recommended that any exposure layers produced with this function are validated with observed fire history using the fire_exp_validate() function.

Spatial Reference:

The exposure raster will be returned in the same CRS as the input hazard layer. A crs must be defined if the outputs will be used in other functions in this package.

Spatial resolution:

For a specified transmission distance, the spatial resolution must be at least 3 times finer. For example, for a transmission distance of 300 meters the input data should have a resolution of 100 meters or finer.

6 fire_exp_dir

Value

SpatRaster object of exposure values

See Also

```
fire_exp() for background information
```

Examples

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))
# compute long range exposure with custom disance of 800 m
exposure800 <- fire_exp_adjust(hazard, tdist = 800)</pre>
```

fire_exp_dir

Conduct a directional exposure assessment

Description

fire_exp_dir() returns a SpatVector of linear transects toward a value. Transects are assessed as viable wildfire pathways by intersecting them with areas of high exposure.

Usage

```
fire_exp_dir(
  exposure,
  value,
  t_lengths = c(5000, 5000, 5000),
  interval = 1,
  thresh_exp = 0.6,
  thresh_viable = 0.8,
  table = FALSE
)
```

Arguments

exposure SpatRaster (e.g. from fire_exp())

value Spatvector of value as a point or simplified polygon

t_lengths (Optional) A vector of three numeric values. The length of each transect starting from the value in meters. The default is c(5000, 5000, 5000).

interval (Optional) Numeric. The degree interval at which to draw the transects for analysis. Can be one of 0.25, 0.5, 1, 2, 3, 4, 5, 6, 8, or 10 (factors of 360, ensures

even spacing). The default is 1.

fire_exp_dir 7

thresh_exp (optional) Numeric. The exposure value to use to define high exposure as a

proportion. Must be between 0-1. The default is 0.6.

thresh_viable (optional) Numeric. The minimum intersection of a transect with a high expo-

sure patch to be defined as a viable pathway as a proportion. Must be between

0-1. The default is 0.8.

table Boolean, when TRUE: returns a table instead of a feature. The default is FALSE.

Details

fire_exp_dir() automates the directional vulnerability assessment methods documented in Beverly and Forbes (2023). This analysis is used to assess linear wildfire vulnerability on the landscape in a systematic radial sampling pattern. This is a landscape scale process, so the exposure raster used should also be landscape scale. Use tdist = "1" when preparing data with fire_exp() for use with this function. See fire_exp() details for more information.

The output line features will have the attribute 'viable' which can be used to visualize the pathways. Outputs can be visualized with fire_exp_dir_plot(), fire_exp_dir_map(), or exported as a spatial feature.

Spatial Reference:

The inputs for the exposure and value layer must have the same coordinate reference system (CRS) defined. The transects will be returned in the same CRS as the inputs.

This function draws the transects by calculating the end point of a transect by finding the shortest path along the WGS84 (EPSG:4326) ellipsoid at a given bearing and distance. The value input is reprojected from the input CRS to latitude and longitude using WGS84 for the calculations. After the transects are created, they are projected to match the CRS of the input exposure and value layer. The lengths of the projected transects will be effected by the scale factor of the input CRS; however, the geodesic lengths are maintained.

Value feature:

The value feature can be provided as a point or a simplified polygon.

If using a point feature the analysis can be sensitive to the placement of a point. For example, if using a point to represent a large town a point placed at the centroid will likely have different outputs than a point placed at the edge of the community due to the arrangement of lower exposure values typical of a built environment.

An option to use a simplified polygon has been added to this function for values that may be too large to represent with a single point. The polygon should be drawn with the consideration of the following or the function will not be able to run. The polygon must be a single part polygon with no holes. The polygon should have a smooth and simple shape, ideally circular or ellipsoidal. The polygon should also have an approximate radius of less than 5000 meters from the center. If the area of interest is larger than this then consider using multiple assessments.

Default Values:

The default values are based on the methods used and validated in Alberta, Canada by Beverly and Forbes (2023). Options have been added to the function to allow these values to be adjusted by the user if required. Adjusting these values can lead to unexpected and uncertain results.

Adjusting the transects:

8 fire_exp_dir

The drawing of the transects can be customized by varying the intervals and segment lengths if desired. Adjustments to the interval and t_lengths parameters will effect how much of the exposure data is being captured by the transects. If both parameters are being adjusted some trigonometry might be required to find the optimal combination of the parameters to ensure distances between the transects make sense for the intended application. The resolution of the exposure raster may also be a factor in these decisions.

Interval:

The interval parameter defines how many transects are drawn. The default of 1 draws a transect at every whole degree from 1-360. This outputs a total of 1080 transects, 360 for each segment. Increasing the interval will output less transects and process faster. When the interval is increased, the distance between the ends of the transects will also be increased. For example: the terminus of 15000 meter transects (the default) drawn every 1 degree (the default) will be approximately 250 meters apart, but if drawn at 10 degree intervals will be approximately 2500 meters apart. Larger intervals will increase speed and processing time, but might not capture potential pathways between transects farther from the value.

Lengths:

The t_lengths parameter allows a custom distance to be defined for the three transect segments in meters. Lengths can be increased or decreased. The segments can also be different lengths if desired

Adjusting the thresholds:

Threshold adjustments should only be considered if validation within the area of interest have been done. The function fire_exp_validate() has been included with this package to make the process easier, but still requires significant time, data, and understanding.

High exposure:

The thresh_exp parameter can be adjusted to define the minimum exposure value to be considered for the directional assessment. The default value of 0.6 is based on the findings of Beverly et al. (2021) who showed that observed fires burned preferentially in areas where wildfire exposure values exceed 60%. Adjusting this value is only recommended after a validation of wildfire exposure has been conducted in the area of interest.

Viability:

The thresh_viable parameter defines the minimum intersection with high exposure areas to be considered a viable pathway. The default value of 0.8 was determined by Beverly and Forbes (2023) by drawing continuous linear transects within burned areas to represent observed pathways. It was found that the average intersection with patches of pre-fire high exposure was 80%. This methodology could be repeated in the users area of interest.

Value

a SpatVector of the transects with the attributes: 'deg' = degree, 'seg' = segment, and 'viable'. The transects will be returned with the same CRS as the input features.

If table = TRUE: a data frame is returned instead with an additional attribute 'wkt', which is a Well Known Text (WKT) string of transect geometries (coordinate reference system: WGS84).

References

Beverly JL, Forbes AM (2023) Assessing directional vulnerability to wildfire. *Natural Hazards* **117**, 831-849. **DOI**

fire_exp_dir_map 9

Beverly JL, McLoughlin N, Chapman E (2021) A simple metric of landscape fire exposure. *Landscape Ecology* **36**, 785-801. DOI

Examples

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))
# generate an example point
point_wkt <- "POINT (400000 6050000)"
point <- terra::vect(point_wkt, crs = hazard)
# compute exposure metric
exposure <- fire_exp(hazard)
# assess directional exposure
fire_exp_dir(exposure, point)</pre>
```

fire_exp_dir_map

Map directional exposure

Description

fire_exp_dir_map() plots directional exposure transects onto a map.

Usage

```
fire_exp_dir_map(
   transects,
   value,
   zoom_level = 10,
   labels,
   title = "Directional Vulnerability"
)
```

Arguments

transects	SpatVector. Output from fire_exp_dir()
value	(Optional) SpatVector. Adds the value to the map. Use the same value feature used to generate the transects with fire_exp_dir()
zoom_level	(Optional). Numeric. set the zoom level for the base map tile. See details. The default is 10.
labels	(Optional) a vector of three strings. Custom formatting for the distances in the legend. If left blank, the function will automatically label the distances in meters.
title	(Optional) String. A custom title for the plot. The default is "Directional Vulnerability"

10 fire_exp_dir_multi

Details

This function returns a standardized map with basic cartographic elements.

The plot is returned as a ggplot object which can be exported/saved to multiple image file formats.

Spatial reference:

This function dynamically pulls map tiles for a base map. The inputs are projected to WGS 84/Pseudo-Mercator (EPSG:3857) to align them with the map tiles.

Zoom level:

The map tile zoom level may need to be adjusted. If the base map is blurry, increase the zoom level. Higher zoom levels will slow down the function, so only increase if necessary. Reference the OpenStreetMap Wiki for more information on zoom levels.

Value

a map of directional exposure transects as a ggplot object

Examples

fire_exp_dir_multi

Summarize or plot directional load for multiple values

Description

fire_exp_dir_multi() summarizes the directional vulnerability load for multiple points in a study area in a table or a plot.

Usage

```
fire_exp_dir_multi(exposure, values, plot = FALSE, full = FALSE, title, ...)
```

fire_exp_dir_multi

Arguments

exposure	SpatRaster from fire_exp()
values	Spatvector of value as a point or simplified polygon
plot	Boolean, when TRUE: returns a standardized directional plot. The default is FALSE.
full	Boolean. Ignored when plot = FALSE. When TRUE: all 3 transect segments must be viable. when FALSE: only the segments from seg2 and seg3 are considered (Default)
title	(Optional) String. Ignored when plot = FALSE. A custom title for the plot. The default is "Directional Vulnerability for Multiple Values"
	arguments passed to fire_exp_dir().

Details

This function summarizes multiple directional vulnerability assessments into a single table or plot. The plot is based on the methods presented in Beverly and Forbes 2023. For each degree, the frequency of input values with a continuous pathway at that trajectory is found. This summary can be useful in identifying trends in directional exposure to values within a regional area of interest.

Continuous pathways can be assessed for the full span of all three directional assessment transect segments, or limited to the outer two segments with the full parameter. If the values being assessed are variable sizes and being represented as points, it is recommended this parameter remains set to FALSE. The inner segment is sensitive to the size of the value when a point is used. Adjusting the parameters for fire_exp_dir() is also supported. See details in fire_exp_dir() for more information.

Value

a data.frame of the features with attributes: value featureID, degree, seg1 (binary), seg2 (binary), seg3 (binary), full (binary), outer (binary). Unless:

• plot = TRUE: a standardized plot as a ggplot object

References

Beverly JL, Forbes AM (2023) Assessing directional vulnerability to wildfire. *Natural Hazards* **117**, 831-849. **DOI**

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))
# generate 10 random example points within the hazard extent
e <- terra::buffer(terra::vect(terra::ext(hazard), crs = hazard), -15500)
points <- terra::spatSample(e, 10)
# compute exposure metric</pre>
```

12 fire_exp_dir_plot

```
exposure <- fire_exp(hazard)
# plot directional load for multiple points
fire_exp_dir_multi(exposure, points, plot = TRUE, interval = 10)</pre>
```

fire_exp_dir_plot

Plot directional exposure in a radial plot

Description

fire_exp_dir_plot() plots the viable directional exposure pathways identified with fire_exp_dir() in a standardized radial plot.

Usage

```
fire_exp_dir_plot(transects, labels, title = "Directional Vulnerability")
```

Arguments

labels (Optional) a vector of three strings. Custom formatting for the distance labels

on the transect segments. If left blank, the function will automatically label the

distances in meters.

title (Optional) String. A custom title for the plot. The default is "Directional

Vulnerability"

Details

The radial plot produced by this function is based on the figures presented in Beverly and Forbes (2023). The plots put the transect origin (the value) at the center as a point, and labels the distances from the value at the end of the transect segments. If the value used to generate the transects was a polygon feature, the transect origins will still be drawn as a center point.

The plot is returned as a ggplot object which can be exported/saved to multiple image file formats.

Value

a ggplot object.

References

Beverly JL, Forbes AM (2023) Assessing directional vulnerability to wildfire. *Natural Hazards* **117**, 831-849. **DOI**

fire_exp_extract 13

Examples

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))
# generate an example point
point_wkt <- "POINT (400000 6050000)"
point <- terra::vect(point_wkt, crs = hazard)
# compute exposure metric
exposure <- fire_exp(hazard)
# generate transects
transects <- fire_exp_dir(exposure, point)
# radial plot
fire_exp_dir_plot(transects)
# customize labels
fire_exp_dir_plot(transects, labels = c("5 km", "10 km", "15 km"))</pre>
```

fire_exp_extract

Extract exposure values to features

Description

fire_exp_extract() extracts the underlying exposure value for each feature in the values layer.

Usage

```
fire_exp_extract(exposure, values)
```

Arguments

```
exposure SpatRaster (e.g. from fire_exp())
values Spatvector of points or polygons
```

Details

This function appends the underlying exposure value to the input feature as a new attribute. The values input can be provided as either points or polygons. The values should be singlepart features (i.e. the attribute table has one row per value). If the values are polygon features both the maximum and mean exposure is computed. Any values outside the extent of the exposure raster will be returned with an exposure of NA.

Outputs from this function can be visualized with fire_exp_extract_vis() or exported as a spatial feature.

14 fire_exp_extract_vis

Spatial Reference:

The inputs for the exposure and values layer must have the same coordinate reference system (CRS) defined. The transects will be returned in the same CRS as the inputs.

Scale:

The spatial resolution of the input exposure raster will effect the output. The exposure value returned by this function are based on the cell value underlying the feature in the values input. Note that if the resolution of the exposure raster is coarse, there may be multiple values within the same cell and the returned values will reflect this. For polygon features, the maximum and mean value of all cells within the boundary of the polygon are used. If the exposure raster is coarse, there may not be more than one cell within the polygon which will result in these values being the same.

Value

a SpatVector object with new attribute(s)

Examples

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))
# read example area of interest geometry
geom_file_path <- "extdata/polygon_geometry.csv"
geom <- read.csv(system.file(geom_file_path, package = "fireexposuR"))
# generate an area of interest polygon with the geometry
aoi <- terra::vect(as.matrix(geom), "polygons", crs = hazard)
# generate random points within the aoi polygon
points <- terra::spatSample(aoi, 100)
# compute exposure
exposure <- fire_exp(hazard)
fire_exp_extract(exposure, points)</pre>
```

fire_exp_extract_vis Visualize exposure to values in a summary table or map

Description

fire_exp_extract_vis() standardizes the visualization of outputs from fire_exp_extract() as a summary table or a map by classifying exposure into predetermined exposure classes.

fire_exp_extract_vis 15

Usage

```
fire_exp_extract_vis(
  values_ext,
  classify = c("local", "landscape", "custom"),
  class_breaks,
  method = c("max", "mean"),
  map = FALSE,
  zoom_level,
  title = "Classified Exposure to Values"
)
```

Arguments

values_ext	Spatvector of points or polygons from fire_exp_extract()
classify	character, either "local", "landscape", or "custom", to specify classification scheme to use. The default is "local". If set to "custom": the parameter class_breaks must be used.
class_breaks	vector of numeric values between 0-1. Ignored unless classify = "custom". See details.
method	character, either "max" or "mean". If values_ext are polygons the default is "max". This parameter is ignored when values_ext are point features.
map	Boolean. When TRUE, a map is returned as a ggplot object. The default is FALSE.
zoom_level	(Optional). Numeric. Ignored when map = FALSE. set the zoom level for the base map tile. See details. Defaults if:
	 classify = "local" or "custom" the zoom level default is 12 classify = "landscape" the zoom level default is 7
title	(Optional) String. Ignored when map = FALSE. A custom title for the plot. The default is "Classified Exposure to Values"

Details

This function visualizes the outputs from fire_exp_extract() with classes. Classes can be chosen from the pre-set "local" and "landscape" options, or customized. To use a custom classification scheme, it should be defined with a list of numeric vectors defining the upper limits of the breaks. A Nil class is added automatically for exposure values of exactly zero.

Local classification breaks are predefined as c(0.15, 0.3, 0.45, 1):

```
Nil (0)
0 - 0.15
0.15 - 0.3
0.3 - 0.45
```

• 0.45 - 1

#' Landscape classification breaks are predefined as c(0.2, 0.4, 0.6, 0.8, 1):

• Nil (0)

16 fire_exp_extract_vis

- 0 0.2
- 0.2 0.4
- 0.4 0.6
- 0.6 0.8
- 0.8 1

Spatial reference:

This function dynamically pulls map tiles for a base map when map = TRUE. The inputs are projected to WGS 84/Pseudo-Mercator (EPSG:3857) to align them with the map tiles.

Zoom level:

The map tile zoom level may need to be adjusted. If the base map is blurry, increase the zoom level. Higher zoom levels will slow down the function, so only increase if necessary. Reference the OpenStreetMap Wiki for more information on zoom levels.

Value

a summary table is returned as a data frame object, Unless: map = TRUE: a ggplot object

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))</pre>
# read example area of interest geometry
geom_file_path <- "extdata/polygon_geometry.csv"</pre>
geom <- read.csv(system.file(geom_file_path, package = "fireexposuR"))</pre>
# generate an area of interest polygon with the geometry
aoi <- terra::vect(as.matrix(geom), "polygons", crs = hazard)</pre>
# generate random points within the aoi polygon
points <- terra::spatSample(aoi, 100)</pre>
# compute exposure
exposure <- fire_exp(hazard)</pre>
values_exp <- fire_exp_extract(exposure, points)</pre>
# summarize example points in a table
fire_exp_extract_vis(values_exp, classify = "local")
# visualize example points in standardized map
fire_exp_extract_vis(values_exp, map = TRUE)
```

fire_exp_map_class 17

fire_exp_map_class

Map exposure with a classified scale

Description

fire_exp_map_class() produces a standardized map by classifying exposure into predetermined exposure classes.

Usage

```
fire_exp_map_class(
  exposure,
  aoi,
  classify = c("local", "landscape", "custom"),
  class_breaks,
  zoom_level,
  title = "Classified Exposure"
)
```

Arguments

exposure	SpatRaster (e.g. from fire_exp())
aoi	(Optional) SpatVector of an area of interest to mask exposure
classify	character, either "local", "landscape", or "custom", to specify classification scheme to use. The default is "local". If set to "custom": the parameter class_breaks must be used.
class_breaks	vector of numeric values between 0-1 of the upper limits of each custom class. Ignored unless classify = "custom". See details.
zoom_level	(Optional) numeric, set the zoom level for the basemap based on the extent of your data if defaults are not appropriate. See details. Defaults if:
	 classify = "local" or "custom" the zoom level default is 12 classify = "landscape" the zoom level default is 7
title	(Optional) String. A custom title for the plot. The default is "Classified Exposure"

Details

This function returns a standardized map with basic cartographic elements.

The plot is returned as a ggplot object which can be exported/saved to multiple image file formats.

This function visualizes the outputs from fire_exp() with classes. Classes can be chosen from the pre-set "local" and "landscape" options, or customized. To use a custom classification scheme, it should be defined with a list of numeric vectors defining the upper limits of the breaks. A Nil class is added automatically for exposure values of exactly zero.

Local classification breaks are predefined as c(0.15, 0.3, 0.45, 1):

18 fire_exp_map_class

- Nil (0)
- 0 0.15
- 0.15 0.3
- 0.3 0.45
- 0.45 1

Landscape classification breaks are predefined as c(0.2, 0.4, 0.6, 0.8, 1):

- Nil (0)
- 0 0.2
- 0.2 0.4
- 0.4 0.6
- 0.6 0.8
- 0.8 1

Spatial reference:

This function dynamically pulls map tiles for a base map. The inputs are projected to WGS 84/Pseudo-Mercator (EPSG:3857) to align them with the map tiles.

Zoom level:

The map tile zoom level may need to be adjusted. If the base map is blurry, increase the zoom level. Higher zoom levels will slow down the function, so only increase if necessary. Reference the OpenStreetMap Wiki for more information on zoom levels.

Value

a standardized map is returned as a ggplot object

See Also

```
fire_exp_map_class()
```

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))
# read example area of interest geometry
geom_file_path <- "extdata/polygon_geometry.csv"
geom <- read.csv(system.file(geom_file_path, package = "fireexposuR"))
# generate example area of interest polygon with geometry
aoi <- terra::vect(as.matrix(geom), "polygons", crs = hazard)
# compute exposure
exposure <- fire_exp(hazard)
fire_exp_map_class(exposure, aoi, classify = "local")</pre>
```

fire_exp_map_cont 19

fire_exp_map_cont

Description

fire_exp_map_cont() produces a standardized map of exposure with a continuous scale for the full extent of the data or masked to an area of interest.

Usage

```
fire_exp_map_cont(exposure, aoi, title = "Wildfire Exposure")
```

Arguments

exposure	SpatRaster from fire_exp()
aoi	(Optional) SpatVector of an area of interest to mask the exposure

title (Optional) String. A custom title for the plot. The default is "Wildfire Exposure"

Details

This function returns a standardized map with basic cartographic elements. The exposure values are mapped using a continuous scale. There is no base map added with this function.

The plot is returned as a ggplot object which can be exported/saved to multiple image file formats.

Spatial Reference:

The map will be drawn using the same CRS as the input data.

Value

a map is returned as a ggplot object

See Also

```
fire_exp_map_class()
```

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))
# Compute exposure
exposure <- fire_exp(hazard)
fire_exp_map_cont(exposure)</pre>
```

20 fire_exp_summary

fire_exp_summary

Summarize exposure by class

Description

fire_exp_summary() creates a summary table of area and proportions of exposure in predetermined or custom exposure classes.

Usage

```
fire_exp_summary(
  exposure,
  aoi,
  classify = c("landscape", "local", "custom"),
  class_breaks
)
```

Arguments

exposure SpatRaster from fire_exp()

aoi (optional) SpatVector of an area of interest to mask exposure for summary

classify character, either "local", "landscape", or "custom", to specify classification
 scheme to use. The default is "local". If set to "custom": the parameter
 class_breaks must be used.

class_breaks vector of numeric values between 0-1 of the upper limits of each custom class.
 Ignored unless classify = "custom". See details.

Details

This function summarizes the outputs from fire_exp() with classes. Classes can be chosen from the pre-set "local" and "landscape" options, or customized. To use a custom classification scheme, it should be defined with a list of numeric vectors defining the upper limits of the breaks. A Nil class is added automatically for exposure values of exactly zero.

Local classification breaks are predefined as c(0.15, 0.3, 0.45, 1):

- Nil (0)
- 0 0.15
- 0.15 0.3
- 0.3 0.45
- 0.45 1

Landscape classification breaks are predefined as c(0.2, 0.4, 0.6, 0.8, 1):

- Nil (0)
- 0 0.2

fire_exp_validate 21

- 0.2 0.4
- 0.4 0.6
- 0.6 0.8
- 0.8 1

The table reports the number of pixels, the proportion, and area in hectares and meters squared in each class.

Value

a summary table as a data frame object

Examples

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))
# read example area of interest polygon geometry
geom_file_path <- "extdata/polygon_geometry.csv"
geom <- read.csv(system.file(geom_file_path, package = "fireexposuR"))
aoi <- terra::vect(as.matrix(geom), "polygons", crs = hazard)
# Compute exposure
exposure <- fire_exp(hazard)
# Summary for full extent of data
fire_exp_summary(exposure, classify = "landscape")
# Summary masked to an area of interest
fire_exp_summary(exposure, aoi, classify = "landscape")</pre>
```

fire_exp_validate

Validate exposure with observed fires

Description

For advanced users. fire_exp_validate() compares the proportion of exposure classes in a the study area to the proportion of exposure classes within observed burned areas.

Usage

```
fire_exp_validate(
  burnableexposure,
  fires,
  aoi,
  class_breaks = c(0.2, 0.4, 0.6, 0.8, 1),
  samplesize = 0.005
)
```

22 fire_exp_validate

Arguments

burnableexposure

A SpatRaster of exposure, non-burnable cells should be removed using optional

parameter no_burn = in fire_exp().

fires A SpatVector of observed fire perimeters

aoi (Optional) A SpatVector that delineates an area of interest

class_breaks (Optional) vector of numeric values between 0-1 of the upper limits of each

class. The default is c(0.2, 0.4, 0.6, 0.8, 1). See details.

samplesize Proportion of areas to sample. The default is 0.005 (0.5%)

Details

This function automates a simple validation method to assess if fire burns preferentially in areas with high exposure. The methods, and figure produced with fire_exp_validate_plot(), are based on Beverly et al. (2021).

The function requires an exposure raster produced for a past point in time. Cells that cannot burn, or do not represent natural land cover should be removed by setting the no_burn parameter in fire_exp() or fire_exp_adjust().

The function also requires fire perimeter data. Currently, the function takes the fires as a Vector of polygons because that is typically how fire boundaries are stored in spatial databases. The fires input data should include all of the burned area that has occurred following the time period the input exposure layer was produced for. It is up to the user to determine the appropriate amount of burned area required for a meaningful assessment.

A random sample is taken to account for spatial autocorrelation, the sampled location results can be used to test for significant differences. The sample size can be adjusted. The sample size represents a proportion of cells, the default is 0.005 (0.5%). It is the user's responsibility to set an appropriate sample size.

The class breaks can be customized from the default of 0.2 intervals by setting the class_breaks parameter. A class of Nil is automatically added for values exactly equal to 0.

Value

a table of number of cells (n) and proportions (prop) of exposure classes within a sampled area (Sample) and across the full extent (Total).for the full extent of the exposure data (expected) and only within the burned areas (observed).

References

Beverly JL, McLoughlin N, Chapman E (2021) A simple metric of landscape fire exposure. *Landscape Ecology* **36**, 785-801. DOI

See Also

fire_exp_validate_plot()

fire_exp_validate_plot

23

Examples

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))</pre>
# generate example non-burnable cells data
geom_file_path <- "extdata/polygon_geometry.csv"</pre>
geom <- read.csv(system.file(geom_file_path, package = "fireexposuR"))</pre>
polygon <- terra::vect(as.matrix(geom), "polygons", crs = hazard)</pre>
no_burn <- terra::rasterize(polygon, hazard)</pre>
# generate example fire polygons by buffering random points
points <- terra::spatSample(terra::rescale(hazard, 0.8),</pre>
                              30, as.points = TRUE)
fires <- terra::buffer(points, 800)</pre>
# PLEASE NOTE THIS EXAMPLE DATA DOES NOT GENERATE MEANINGFUL RESULTS
# compute exposure and remove non-burnable cells
exposure <- fire_exp(hazard, no_burn = no_burn)</pre>
# validation table
fire_exp_validate(exposure, fires)
```

fire_exp_validate_plot

Visualize validation outputs in a plot

Description

fire_exp_validate_plot() Visualizes the results from fire_exp_validate() in a bar plot

Usage

```
fire_exp_validate_plot(
  validation_table,
  what = c("both", "total", "sample"),
  title
)
```

Arguments

```
validation_table
```

The output table from fire_exp_validate()

what string. Which plot should be returned? Can be sample, total, or "both" (De-

fault)

title Optional. String. Add a custom title to the plot.

Value

a ggplot object

See Also

```
fire_exp_validate()
```

```
# read example hazard data
hazard_file_path <- "extdata/hazard.tif"</pre>
hazard <- terra::rast(system.file(hazard_file_path, package = "fireexposuR"))</pre>
# generate example non-burnable cells data
geom_file_path <- "extdata/polygon_geometry.csv"</pre>
geom <- read.csv(system.file(geom_file_path, package = "fireexposuR"))</pre>
polygon <- terra::vect(as.matrix(geom), "polygons", crs = hazard)</pre>
no_burn <- terra::rasterize(polygon, hazard)</pre>
# generate example fire polygons by buffering random points
points <- terra::spatSample(terra::rescale(hazard, 0.8),</pre>
                              30, as.points = TRUE)
fires <- terra::buffer(points, 800)</pre>
# PLEASE NOTE THIS EXAMPLE DATA DOES NOT GENERATE MEANINGFUL RESULTS
# compute exposure and remove non-burnable cells
exposure <- fire_exp(hazard, no_burn = no_burn)</pre>
# results as table
validation_outputs <- fire_exp_validate(exposure, fires)</pre>
# results as bar chart
fire_exp_validate_plot(validation_outputs)
```

Index

```
fire_exp, 2
fire_exp(), 5-7, 11, 13, 17, 19, 20, 22
fire_exp_adjust, 5
fire_exp_adjust(), 3, 22
fire_exp_dir, 6
fire_exp_dir(), 9, 11, 12
fire_exp_dir_map, 9
fire_exp_dir_map(), 7
{\tt fire\_exp\_dir\_multi, 10}
fire_exp_dir_plot, 12
fire_exp_dir_plot(), 7
fire_exp_extract, 13
fire_exp_extract(), 14, 15
fire_exp_extract_vis, 14
fire_exp_extract_vis(), 13
fire_exp_map_class, 17
fire_exp_map_class(), 18, 19
fire\_exp\_map\_cont, 19
fire_exp_summary, 20
fire_exp_validate, 21
fire_exp_validate(), 2, 5, 8, 23, 24
fire_exp_validate_plot, 23
fire_exp_validate_plot(), 22
```