

# Package: opencage (via r-universe)

October 28, 2024

**Type** Package

**Title** Geocode with the OpenCage API

**Version** 0.2.2.9000

**Description** Geocode with the OpenCage API, either from place name to longitude and latitude (forward geocoding) or from longitude and latitude to the name and address of a location (reverse geocoding), see <<https://opencagedata.com>>.

**License** GPL (>= 2)

**URL** <https://docs.ropensci.org/opencage/>,

<https://github.com/ropensci/opencage>

**BugReports** <https://github.com/ropensci/opencage/issues>

**Depends** R (>= 3.4.0)

**Imports** crul (>= 0.5.2), dplyr (>= 0.7.4), jsonlite (>= 1.5), lifecycle, memoise (>= 1.1.0), progress (>= 1.1.2), purrr (>= 0.2.4), ratelimitr (>= 0.4.0), rlang, tibble (>= 1.4.2), tidyr (>= 0.8.0), withr (>= 2.0.0)

**Suggests** knitr (>= 1.19), mockery, rmarkdown (>= 1.8), sf (>= 0.9), testthat (>= 3.1.0)

**VignetteBuilder** knitr

**RdMacros** lifecycle

**Config/testthat/edition** 3

**Encoding** UTF-8

**Language** en-GB

**LazyData** TRUE

**Roxygen** list(markdown = TRUE)

**RoxygenNote** 7.2.3

**Repository** <https://ropensci.r-universe.dev>

**RemoteUrl** <https://github.com/ropensci/opencage>

**RemoteRef** main

**RemoteSha** 9b57eefa9725822d00e1e48417f5948eeeb15db1

## Contents

countrycodes . . . . .	2
oc_bbox . . . . .	2
oc_clear_cache . . . . .	4
oc_config . . . . .	5
oc_forward . . . . .	6
oc_forward_df . . . . .	9
oc_points . . . . .	13
oc_reverse . . . . .	14
oc_reverse_df . . . . .	17
opencage-deprecated . . . . .	19
opencage_forward . . . . .	20
opencage_reverse . . . . .	22
<b>Index</b>	<b>24</b>

---

countrycodes	<i>Country codes</i>
--------------	----------------------

---

### Description

Country codes

### Format

All possible ISO 3166-1 Alpha 2 standard country codes.

### Examples

```
data("countrycodes")
```

---

oc_bbox	<i>List of bounding boxes for OpenCage queries</i>
---------	--

---

### Description

Create a list of bounding boxes for OpenCage queries.

**Usage**

```

oc_bbox(...)

## S3 method for class 'numeric'
oc_bbox(xmin, ymin, xmax, ymax, ...)

## S3 method for class 'data.frame'
oc_bbox(data, xmin, ymin, xmax, ymax, ...)

## S3 method for class 'bbox'
oc_bbox(bbox, ...)

```

**Arguments**

...	Ignored.
xmin	Minimum longitude (also known as min_lon, southwest_lng, west, or left).
ymin	Minimum latitude (also known as min_lat, southwest_lat, south, or bottom).
xmax	Maximum longitude (also known as max_lon, northeast_lng, east, or right).
ymax	Maximum latitude (also known as max_lat, northeast_lat, north, or top).
data	A data.frame containing at least 4 columns with xmin, ymin, xmax, and ymax values, respectively.
bbox	A bbox object, see sf::st_bbox.

**Value**

A list of bounding boxes, each of class bbox.

**Examples**

```

oc_bbox(-5.63160, 51.280430, 0.278970, 51.683979)

xdf <-
  data.frame(
    place = c("Hamburg", "Hamburg"),
    northeast_lat = c(54.0276817, 42.7397729),
    northeast_lng = c(10.3252805, -78.812825),
    southwest_lat = c(53.3951118, 42.7091669),
    southwest_lng = c(8.1053284, -78.860521)
  )
oc_bbox(
  xdf,
  southwest_lng,
  southwest_lat,
  northeast_lng,
  northeast_lat
)

# create bbox list column with dplyr

```

```
library(dplyr)
xdf %>%
  mutate(
    bbox =
      oc_bbox(
        southwest_lng,
        southwest_lat,
        northeast_lng,
        northeast_lat
      )
  )

# create bbox list from a simple features bbox
if (requireNamespace("sf", quietly = TRUE)) {
  library(sf)
  bbox <- st_bbox(c(xmin = 16.1, xmax = 16.6, ymax = 48.6, ymin = 47.9),
    crs = 4326
  )
  oc_bbox(bbox)
}
```

---

oc_clear_cache	<i>Clear the opencage cache</i>
----------------	---------------------------------

---

## Description

Forget past results and reset the **opencage** cache.

## Usage

```
oc_clear_cache()
```

## Examples

```
system.time(oc_reverse(latitude = 10, longitude = 10))
system.time(oc_reverse(latitude = 10, longitude = 10))
oc_clear_cache()
system.time(oc_reverse(latitude = 10, longitude = 10))
```

---

oc_config	<i>Configure settings</i>
-----------	---------------------------

---

## Description

Configure session settings for **opencage**.

## Usage

```
oc_config(
  key = Sys.getenv("OPENCAGE_KEY"),
  rate_sec = getOption("oc_rate_sec", default = 1L),
  no_record = getOption("oc_no_record", default = TRUE),
  show_key = getOption("oc_show_key", default = FALSE),
  ...
)
```

## Arguments

key	Your OpenCage API key as a character vector of length one. Do not pass the key directly as a parameter, though. See details.
rate_sec	Numeric vector of length one. Sets the maximum number of requests sent to the OpenCage API per second. Defaults to the value set in the <code>oc_rate_sec</code> option, or, in case that does not exist, to 1L.
no_record	Logical vector of length one. When TRUE, OpenCage will not create log entries of the queries and will not cache the geocoding requests. Defaults to the value set in the <code>oc_no_record</code> option, or, in case that does not exist, to TRUE.
show_key	Logical vector of length one. This is only relevant when debugging <code>oc_forward()</code> or <code>oc_reverse()</code> calls with the <code>return = "url_only"</code> argument. When TRUE, the result will show your OpenCage API key in the URL as stored in the <code>OPENCAGE_KEY</code> environment variable. When not TRUE, the API key will be replaced with the string <code>OPENCAGE_KEY</code> . <code>show_key</code> defaults to the value set in the <code>oc_show_key</code> option, or, in case that does not exist, to FALSE.
...	Ignored.

## Set your OpenCage API key

**opencage** will conveniently retrieve your API key if it is saved in the environment variable `"OPENCAGE_KEY"`. `oc_config()` will help to set that environment variable. Do not pass the key directly as a parameter to the function, though, as you risk exposing it via your script or your history. There are three safer ways to set your API key instead:

1. Save your API key as an environment variable in `.Renviron` as described in [What They Forgot to Teach You About R](#) or [Efficient R Programming](#). From there it will be fetched by all functions that call the OpenCage API. You do not even have to call `oc_config()` to set your key; you can start geocoding right away. If you have the **usethis** package installed, you can

edit your `.Renviron` with `usethis::edit_r_environ()`. We strongly recommend storing your API key in the user-level `.Renviron`, as opposed to the project-level. This makes it less likely you will share sensitive information by mistake.

2. If you use a package like **keyring** to store your credentials, you can safely pass your key in a script with a function call like this `oc_config(key = keyring::key_get("opencage"))`.
3. If you call `oc_config()` in an `base::interactive()` session and the `OPENCAGE_KEY` environment variable is not set, it will prompt you to enter the key in the console.

### Set your OpenCage API rate limit

The rate limit allowed by the API depends on the OpenCage plan you purchased and ranges from 1 request/sec for the "Free Trial" plan to 15 requests/sec for the "Medium" or "Large" plans, see <https://opencagedata.com/pricing> for details and up-to-date information. You can set the rate limit persistently across sessions by setting an `oc_rate_sec` option in your `.Rprofile`. If you have the **usethis** package installed, you can edit your `.Rprofile` with `usethis::edit_r_profile()`.

### Prevent query logging and caching

By default, OpenCage will store your queries in its server logs and will cache the forward geocoding requests on their side. They do this in order to speed up response times and to be able to debug errors and improve their service. Logs are automatically deleted after six months according to OpenCage's [page on data protection and GDPR](#).

If you set `no_record` to `TRUE`, the query contents are not logged nor cached. OpenCage still records that you made a request, but not the specific query you made. `oc_config(no_record = TRUE)` sets the `oc_no_record` option for the active R session, so it will be used for all subsequent OpenCage queries. You can set the `oc_no_record` option persistently across sessions in your `.Rprofile`.

For increased privacy **opencage** sets `no_record` to `TRUE`, by default. Please note, however, that **opencage** always caches the data it receives from the OpenCage API locally, but only for as long as your R session is alive.

For more information on OpenCage's policies on privacy and data protection see [their FAQs](#), their [GDPR page](#), and, for the `no_record` parameter, see the relevant [blog post](#).

---

oc\_forward

*Forward geocoding*

---

### Description

Forward geocoding from a character vector of location names to latitude and longitude tuples.

### Usage

```
oc_forward(
  placename,
  return = c("df_list", "json_list", "geojson_list", "url_only"),
  bounds = NULL,
  proximity = NULL,
```

```

countrycode = NULL,
language = NULL,
limit = 10L,
min_confidence = NULL,
no_annotations = TRUE,
roadinfo = FALSE,
no_dedupe = FALSE,
abbrv = FALSE,
address_only = FALSE,
add_request = FALSE,
...
)

```

## Arguments

placename	A character vector with the location names or addresses to be geocoded. If the locations are addresses, see <a href="#">OpenCage's instructions</a> on how to format addresses for best forward geocoding results.
return	A character vector of length one indicating the return value of the function, either a list of tibbles ( <code>df_list</code> , the default), a JSON list ( <code>json_list</code> ), a GeoJSON list ( <code>geojson_list</code> ), or the URL with which the API would be called ( <code>url_only</code> ).
bounds	A list of bounding boxes of length one or <code>length(placename)</code> . Bounding boxes are named numeric vectors, each with four coordinates forming the south-west and north-east corners of the bounding box: <code>list(c(xmin, ymin, xmax, ymax))</code> . <code>bounds</code> restricts the possible results to the supplied region. It can be specified with the <code>oc_bbox()</code> helper. For example: <code>bounds = oc_bbox(-0.563160, 51.280430, 0.278970, 51.683979)</code> . Default is <code>NULL</code> .
proximity	A list of points of length one or <code>length(placename)</code> . A point is a named numeric vector of a latitude, longitude coordinate pair in decimal format. <code>proximity</code> provides OpenCage with a hint to bias results in favour of those closer to the specified location. It can be specified with the <code>oc_points()</code> helper. For example: <code>proximity = oc_points(51.9526, 7.6324)</code> . Default is <code>NULL</code> .
countrycode	A two letter code as defined by the <a href="#">ISO 3166-1 Alpha 2</a> standard that restricts the results to the given country or countries. E.g. "AR" for Argentina, "FR" for France, "NZ" for the New Zealand. Multiple countrycodes per placename must be wrapped in a list. Default is <code>NULL</code> .
language	An <a href="#">IETF BCP 47 language tag</a> (such as "es" for Spanish or "pt-BR" for Brazilian Portuguese). OpenCage will attempt to return results in that language. Alternatively you can specify the "native" tag, in which case OpenCage will attempt to return the response in the "official" language(s). In case the language parameter is set to <code>NULL</code> (which is the default), the tag is not recognized, or OpenCage does not have a record in that language, the results will be returned in English.
limit	Numeric vector of integer values to determine the maximum number of results returned for each placename. Integer values between 1 and 100 are allowed. Default is 10.
min_confidence	Numeric vector of integer values between 0 and 10 indicating the precision of the returned result as defined by its geographical extent, (i.e. by the extent of

	the result's bounding box). See the <a href="#">API documentation</a> for details. Only results with at least the requested confidence will be returned. Default is NULL.
no_annotations	Logical vector indicating whether additional information about the result location should be returned. TRUE by default, which means that the results will not contain annotations.
roadinfo	Logical vector indicating whether the geocoder should attempt to match the nearest road (rather than an address) and provide additional road and driving information. Default is FALSE.
no_dedupe	Logical vector (default FALSE), when TRUE the results will not be deduplicated.
abbrv	Logical vector (default FALSE), when TRUE addresses in the formatted field of the results are abbreviated (e.g. "Main St." instead of "Main Street").
address_only	Logical vector (default FALSE), when TRUE only the address details are returned in the formatted field of the results, not the name of a point-of-interest should there be one at this address.
add_request	Logical vector (default FALSE) indicating whether the request is returned again with the results. If the return value is a <code>df_list</code> , the query text is added as a column to the results. <code>json_list</code> results will contain all request parameters, including the API key used! This is currently ignored by OpenCage if return value is <code>geojson_list</code> .
...	Ignored.

### Value

Depending on the return argument, `oc_forward` returns a list with either

- the results as tibbles ("`df_list`", the default),
- the results as JSON specified as a list ("`json_list`"),
- the results as GeoJSON specified as a list ("`geojson_list`"), or
- the URL of the OpenCage API call for debugging purposes ("`url_only`").

When the results are returned as (a list of) tibbles, the column names coming from the OpenCage API are prefixed with "`oc_`".

### See Also

[oc\\_forward\\_df\(\)](#) for inputs as a data frame, or [oc\\_reverse\(\)](#) and [oc\\_reverse\\_df\(\)](#) for reverse geocoding. For more information about the API and the various parameters, see the [OpenCage API documentation](#).

### Examples

```
# Geocode a single location, an address in this case
oc_forward(placename = "Triererstr 15, 99432, Weimar, Deutschland")

# Geocode multiple locations
locations <- c("Nantes", "Hamburg", "Los Angeles")
```



```
oc_forward(placename = locations)

# Use bounding box to help return accurate results
# for each placename
bounds <- oc_bbox(
  xmin = c(-2, 9, -119),
  ymin = c(47, 53, 34),
  xmax = c(0, 10, -117),
  ymax = c(48, 54, 35)
)
oc_forward(placename = locations, bounds = bounds)

# Another way to help specify the desired results
# is with country codes.
oc_forward(
  placename = locations,
  countrycode = c("ca", "us", "co")
)

# With multiple countrycodes per placename
oc_forward(
  placename = locations,
  countrycode = list(c("fr", "ca"), c("de", "us"), c("us", "co"))
)

# Return results in a preferred language if possible
oc_forward(
  placename = c("Brugge", "Mechelen", "Antwerp"),
  language = "fr"
)

# Limit the number of results per placename and return json_list
oc_forward(
  placename = locations,
  bounds = bounds,
  limit = 1,
  return = "json_list"
)
```

---

oc\_forward\_df

*Forward geocoding with data frames*

---

## Description

Forward geocoding from a column or vector of location names to latitude and longitude tuples.

## Usage

```
oc_forward_df(...)
```

```

## S3 method for class 'data.frame'
oc_forward_df(
  data,
  placename,
  bind_cols = TRUE,
  output = c("short", "all"),
  bounds = NULL,
  proximity = NULL,
  countrycode = NULL,
  language = NULL,
  limit = 1L,
  min_confidence = NULL,
  no_annotations = TRUE,
  roadinfo = FALSE,
  no_dedupe = FALSE,
  abbrev = FALSE,
  address_only = FALSE,
  ...
)

## S3 method for class 'character'
oc_forward_df(
  placename,
  output = c("short", "all"),
  bounds = NULL,
  proximity = NULL,
  countrycode = NULL,
  language = NULL,
  limit = 1L,
  min_confidence = NULL,
  no_annotations = TRUE,
  roadinfo = FALSE,
  no_dedupe = FALSE,
  abbrev = FALSE,
  address_only = FALSE,
  ...
)

```

### Arguments

...	Ignored.
data	A data frame.
placename	An unquoted variable name of a character column or vector with the location names or addresses to be geocoded. If the locations are addresses, see <a href="#">OpenCage's instructions</a> on how to format addresses for best forward geocoding results.

bind_cols	When bind_col = TRUE, the default, the results are column bound to data. When FALSE, the results are returned as a new tibble.
output	A character vector of length one indicating whether only latitude, longitude, and formatted address variables ("short", the default), or all variables ("all") variables should be returned.
bounds	A list of length one, or an unquoted variable name of a list column of bounding boxes. Bounding boxes are named numeric vectors, each with 4 coordinates forming the south-west and north-east corners of the bounding box: list(c(xmin, ymin, xmax, ymax)). bounds restricts the possible results to the supplied region. It can be specified with the <code>oc_bbox()</code> helper. For example: bounds = oc_bbox(-0.563160, 51.280430, 0.278970, 51.683979). Default is NULL.
proximity	A list of length one, or an unquoted variable name of a list column of points. Points are named numeric vectors with latitude, longitude coordinate pairs in decimal format. proximity provides OpenCage with a hint to bias results in favour of those closer to the specified location. It can be specified with the <code>oc_points()</code> helper. For example: proximity = oc_points(41.40139, 2.12870). Default is NULL.
countrycode	Character vector, or an unquoted variable name of such a vector, of two-letter codes as defined by the <a href="#">ISO 3166-1 Alpha 2</a> standard that restricts the results to the given country or countries. E.g. "AR" for Argentina, "FR" for France, "NZ" for the New Zealand. Multiple countrycodes per placename must be wrapped in a list. Default is NULL.
language	Character vector, or an unquoted variable name of such a vector, of <a href="#">IETF BCP 47 language tags</a> (such as "es" for Spanish or "pt-BR" for Brazilian Portuguese). OpenCage will attempt to return results in that language. Alternatively you can specify the "native" tag, in which case OpenCage will attempt to return the response in the "official" language(s). In case the language parameter is set to NULL (which is the default), the tag is not recognized, or OpenCage does not have a record in that language, the results will be returned in English.
limit	Numeric vector of integer values, or an unquoted variable name of such a vector, to determine the maximum number of results returned for each placename. Integer values between 1 and 100 are allowed. Default is 1.
min_confidence	Numeric vector of integer values, or an unquoted variable name of such a vector, between 0 and 10 indicating the precision of the returned result as defined by its geographical extent, (i.e. by the extent of the result's bounding box). See the <a href="#">API documentation</a> for details. Only results with at least the requested confidence will be returned. Default is NULL).
no_annotations	Logical vector, or an unquoted variable name of such a vector, indicating whether additional information about the result location should be returned. TRUE by default, which means that the results will not contain annotations.
roadinfo	Logical vector, or an unquoted variable name of such a vector, indicating whether the geocoder should attempt to match the nearest road (rather than an address) and provide additional road and driving information. Default is FALSE.
no_dedupe	Logical vector, or an unquoted variable name of such a vector. Default is FALSE. When TRUE the results will not be deduplicated.

abbrv	Logical vector, or an unquoted variable name of such a vector. Default is FALSE. When TRUE addresses in the oc_formatted variable of the results are abbreviated (e.g. "Main St." instead of "Main Street").
address_only	Logical vector, or an unquoted variable name of such a vector. Default is FALSE. When TRUE only the address details are returned in the oc_formatted variable of the results, not the name of a point-of-interest should there be one at this address.

## Value

A tibble. Column names coming from the OpenCage API are prefixed with "oc\_".

## See Also

[oc\\_forward\(\)](#) for inputs as vectors, or [oc\\_reverse\(\)](#) and [oc\\_reverse\\_df\(\)](#) for reverse geocoding. For more information about the API and the various parameters, see the [OpenCage API documentation](#).

## Examples

```
library(tibble)
df <- tibble(
  id = 1:3,
  locations = c("Nantes", "Hamburg", "Los Angeles")
)

# Return lat, lng, and formatted address
oc_forward_df(df, placename = locations)

# Return more detailed information about the locations
oc_forward_df(df, placename = locations, output = "all")

# Do not column bind results to input data frame
oc_forward_df(df, placename = locations, bind_cols = FALSE)

# Add more results by changing the limit from the default of 1.
oc_forward_df(df, placename = locations, limit = 5)

# Restrict results to a given bounding box
oc_forward_df(df,
  placename = locations,
  bounds = oc_bbox(-5, 45, 15, 55)
)

# oc_forward_df accepts unquoted column names for all
# arguments except bind_cols and output.
# This makes it possible to build up more detailed queries
# through the data frame passed to the data argument.

df2 <- add_column(df,
```

```

    bounds = oc_bbox(
      xmin = c(-2, 9, -119),
      ymin = c(47, 53, 34),
      xmax = c(0, 10, -117),
      ymax = c(48, 54, 35)
    ),
    limit = 1:3,
    countrycode = c("ca", "us", "co"),
    language = c("fr", "de", "en")
  )

# Use the bounds column to help return accurate results and
# language column to specify preferred language of results
oc_forward_df(df2,
  placename = locations,
  bounds = bounds,
  language = language
)

# Different limit of results for each placename
oc_forward_df(df2,
  placename = locations,
  limit = limit
)

# Specify the desired results by the countrycode column
oc_forward_df(df2,
  placename = locations,
  countrycode = countrycode
)

```

---

oc\_points

*List of points for OpenCage queries*


---

### Description

Create a list of points (latitude/longitude coordinate pairs) for OpenCage queries.

### Usage

```

oc_points(...)

## S3 method for class 'numeric'
oc_points(latitude, longitude, ...)

## S3 method for class 'data.frame'
oc_points(data, latitude, longitude, ...)

```

### Arguments

... Ignored.  
latitude, longitude Numeric vectors of latitude and longitude values.  
data A data.frame containing at least 2 columns with latitude and longitude values.

### Value

A list of points. Each point is a named vector of length 2 containing a latitude/longitude coordinate pair.

### Examples

```
oc_points(-21.01404, 55.26077)

xdf <-
  data.frame(
    place = c("Hamburg", "Los Angeles"),
    lat = c(53.5503, 34.0536),
    lon = c(10.0006, -118.2427)
  )
oc_points(
  data = xdf,
  latitude = lat,
  longitude = lon
)

# create a list column with points with dplyr
library(dplyr)
xdf %>%
  mutate(
    points =
      oc_points(
        lat,
        lon
      )
  )
)
```

---

oc\_reverse

*Reverse geocoding*

---

### Description

Reverse geocoding from numeric vectors of latitude and longitude pairs to the names and addresses of a location.

**Usage**

```

oc_reverse(
  latitude,
  longitude,
  return = c("df_list", "json_list", "geojson_list", "url_only"),
  language = NULL,
  min_confidence = NULL,
  no_annotations = TRUE,
  roadinfo = FALSE,
  no_dedupe = FALSE,
  abbrev = FALSE,
  address_only = FALSE,
  add_request = FALSE,
  ...
)

```

**Arguments**

latitude, longitude	Numeric vectors of latitude and longitude values.
return	A character vector of length one indicating the return value of the function, either a list of tibbles ( <code>df_list</code> , the default), a JSON list ( <code>json_list</code> ), a GeoJSON list ( <code>geojson_list</code> ), or the URL with which the API would be called ( <code>url_only</code> ).
language	An <b>IETF BCP 47 language tag</b> (such as "es" for Spanish or "pt-BR" for Brazilian Portuguese). OpenCage will attempt to return results in that language. Alternatively you can specify the "native" tag, in which case OpenCage will attempt to return the response in the "official" language(s). In case the language parameter is set to NULL (which is the default), the tag is not recognized, or OpenCage does not have a record in that language, the results will be returned in English.
min_confidence	Numeric vector of integer values between 0 and 10 indicating the precision of the returned result as defined by its geographical extent, (i.e. by the extent of the result's bounding box). See the <b>API documentation</b> for details. Only results with at least the requested confidence will be returned. Default is NULL.
no_annotations	Logical vector indicating whether additional information about the result location should be returned. TRUE by default, which means that the results will not contain annotations.
roadinfo	Logical vector indicating whether the geocoder should attempt to match the nearest road (rather than an address) and provide additional road and driving information. Default is FALSE.
no_dedupe	Logical vector (default FALSE), when TRUE the results will not be deduplicated.
abbrev	Logical vector (default FALSE), when TRUE addresses in the formatted field of the results are abbreviated (e.g. "Main St." instead of "Main Street").
address_only	Logical vector (default FALSE), when TRUE only the address details are returned in the formatted field of the results, not the name of a point-of-interest should there be one at this address.

add_request	Logical vector (default FALSE) indicating whether the request is returned again with the results. If the return value is a <code>df_list</code> , the query text is added as a column to the results. <code>json_list</code> results will contain all request parameters, including the API key used! This is currently ignored by OpenCage if return value is <code>geojson_list</code> .
...	Ignored.

## Value

Depending on the return argument, `oc_reverse` returns a list with either

- the results as tibbles ("`df_list`", the default),
- the results as JSON specified as a list ("`json_list`"),
- the results as GeoJSON specified as a list ("`geojson_list`"), or
- the URL of the OpenCage API call for debugging purposes ("`url_only`").

When the results are returned as (a list of) tibbles, the column names coming from the OpenCage API are prefixed with "`oc_`".

## See Also

[oc\\_reverse\\_df\(\)](#) for inputs as a data frame, or [oc\\_forward\(\)](#) and [oc\\_reverse\(\)](#) for forward geocoding. For more information about the API and the various parameters, see the [OpenCage API documentation](#).

## Examples

```
# Reverse geocode a single location
oc_reverse(latitude = -36.85007, longitude = 174.7706)

# Reverse geocode multiple locations
lat <- c(47.21864, 53.55034, 34.05369)
lng <- c(-1.554136, 10.000654, -118.242767)

oc_reverse(latitude = lat, longitude = lng)

# Return results in a preferred language if possible
oc_reverse(
  latitude = lat, longitude = lng,
  language = "fr"
)

# Return results as a json list
oc_reverse(
  latitude = lat, longitude = lng,
  return = "json_list"
)
```



---

oc_reverse_df	<i>Reverse geocoding with data frames</i>
---------------	---

---

## Description

Reverse geocoding from latitude and longitude pairs to the names and addresses of a location.

## Usage

```
oc_reverse_df(...)  
  
## S3 method for class 'data.frame'  
oc_reverse_df(  
  data,  
  latitude,  
  longitude,  
  bind_cols = TRUE,  
  output = c("short", "all"),  
  language = NULL,  
  min_confidence = NULL,  
  roadinfo = FALSE,  
  no_annotations = TRUE,  
  no_dedupe = FALSE,  
  abbrev = FALSE,  
  address_only = FALSE,  
  ...  
)  
  
## S3 method for class 'numeric'  
oc_reverse_df(  
  latitude,  
  longitude,  
  output = c("short", "all"),  
  language = NULL,  
  min_confidence = NULL,  
  no_annotations = TRUE,  
  no_dedupe = FALSE,  
  abbrev = FALSE,  
  address_only = FALSE,  
  ...  
)
```

## Arguments

...	Ignored.
data	A data frame.

latitude, longitude	Unquoted variable names of numeric columns or vectors of latitude and longitude values.
bind_cols	When <code>bind_col = TRUE</code> , the default, the results are column bound to data. When <code>FALSE</code> , the results are returned as a new tibble.
output	A character vector of length one indicating whether only the formatted address ("short", the default) or all variables ("all") variables should be returned.
language	Character vector, or an unquoted variable name of such a vector, of <a href="#">IETF BCP 47 language tags</a> (such as "es" for Spanish or "pt-BR" for Brazilian Portuguese). OpenCage will attempt to return results in that language. Alternatively you can specify the "native" tag, in which case OpenCage will attempt to return the response in the "official" language(s). In case the language parameter is set to <code>NULL</code> (which is the default), the tag is not recognized, or OpenCage does not have a record in that language, the results will be returned in English.
min_confidence	Numeric vector of integer values, or an unquoted variable name of such a vector, between 0 and 10 indicating the precision of the returned result as defined by its geographical extent, (i.e. by the extent of the result's bounding box). See the <a href="#">API documentation</a> for details. Only results with at least the requested confidence will be returned. Default is <code>NULL</code> .
roadinfo	Logical vector, or an unquoted variable name of such a vector, indicating whether the geocoder should attempt to match the nearest road (rather than an address) and provide additional road and driving information. Default is <code>FALSE</code> .
no_annotations	Logical vector, or an unquoted variable name of such a vector, indicating whether additional information about the result location should be returned. <code>TRUE</code> by default, which means that the results will not contain annotations.
no_dedupe	Logical vector, or an unquoted variable name of such a vector. Default is <code>FALSE</code> . When <code>TRUE</code> the results will not be deduplicated.
abbrv	Logical vector, or an unquoted variable name of such a vector. Default is <code>FALSE</code> . When <code>TRUE</code> addresses in the <code>oc_formatted</code> variable of the results are abbreviated (e.g. "Main St." instead of "Main Street").
address_only	Logical vector, or an unquoted variable name of such a vector. Default is <code>FALSE</code> . When <code>TRUE</code> only the address details are returned in the <code>oc_formatted</code> variable of the results, not the name of a point-of-interest should there be one at this address.

### Value

A tibble. Column names coming from the OpenCage API are prefixed with "oc\_".

### See Also

[oc\\_reverse\(\)](#) for inputs as vectors, or [oc\\_forward\(\)](#) and [oc\\_forward\(\)](#) for forward geocoding. For more information about the API and the various parameters, see the [OpenCage API documentation](#).

## Examples

```
library(tibble)
df <- tibble(
  id = 1:4,
  lat = c(-36.85007, 47.21864, 53.55034, 34.05369),
  lng = c(174.7706, -1.554136, 10.000654, -118.242767)
)

# Return formatted address of lat/lng values
oc_reverse_df(df, latitude = lat, longitude = lng)

# Return more detailed information about the locations
oc_reverse_df(df,
  latitude = lat, longitude = lng,
  output = "all"
)

# Return results in a preferred language if possible
oc_reverse_df(df,
  latitude = lat, longitude = lng,
  language = "fr"
)

# oc_reverse_df accepts unquoted column names for all
# arguments except bind_cols and output.
# This makes it possible to build up more detailed queries
# through the data frame passed to the data argument.

df2 <- add_column(df,
  language = c("en", "fr", "de", "en"),
  confidence = c(8, 10, 10, 10)
)

# Use language column to specify preferred language of results
# and confidence column to allow different confidence levels
oc_reverse_df(df2,
  latitude = lat, longitude = lng,
  language = language,
  min_confidence = confidence
)
```

---

opencage-deprecated     *Deprecated functions in opencage*

---

## Description

These functions still work but will be removed (defunct) in the next version.

## Details

- [opencage\\_forward\(\)](#)
- [opencage\\_reverse\(\)](#)
- [opencage\\_key\(\)](#)

---

opencage\_forward      *Forward geocoding*

---

## Description

### [Deprecated]

Deprecated: use `oc_forward` or `oc_forward_df` for forward geocoding.

## Usage

```
opencage_forward(  
  placename,  
  key = opencage_key(),  
  bounds = NULL,  
  countrycode = NULL,  
  language = NULL,  
  limit = 10L,  
  min_confidence = NULL,  
  no_annotations = FALSE,  
  no_dedupe = FALSE,  
  no_record = FALSE,  
  abbrev = FALSE,  
  add_request = TRUE  
)
```

## Arguments

- |           |  |
|-----------|--|
| placename | A character vector with the location names or addresses to be geocoded.<br>If the locations are addresses, see <a href="#">OpenCage's instructions</a> on how to format addresses for best forward geocoding results.  |
| key       | Your OpenCage API key as a character vector of length one. By default, <a href="#">opencage_key()</a> will attempt to retrieve the key from the environment variable <code>OPENCAGE_KEY</code> .   |
| bounds    | A list of bounding boxes of length one or <code>length(placename)</code> . Bounding boxes are named numeric vectors, each with four coordinates forming the south-west and north-east corners of the bounding box: <code>list(c(xmin, ymin, xmax, ymax))</code> . <code>bounds</code> restricts the possible results to the supplied region. It can be specified with the <a href="#">oc_bbox()</a> helper. For example: <code>bounds = oc_bbox(-0.563160, 51.280430, 0.278970, 51.683979)</code> . Default is <code>NULL</code> . |

countrycode	A two letter code as defined by the <a href="#">ISO 3166-1 Alpha 2</a> standard that restricts the results to the given country or countries. E.g. "AR" for Argentina, "FR" for France, "NZ" for the New Zealand. Multiple countrycodes per placename must be wrapped in a list. Default is NULL.
language	An <a href="#">IETF BCP 47 language tag</a> (such as "es" for Spanish or "pt-BR" for Brazilian Portuguese). OpenCage will attempt to return results in that language. Alternatively you can specify the "native" tag, in which case OpenCage will attempt to return the response in the "official" language(s). In case the language parameter is set to NULL (which is the default), the tag is not recognized, or OpenCage does not have a record in that language, the results will be returned in English.
limit	Numeric vector of integer values to determine the maximum number of results returned for each placename. Integer values between 1 and 100 are allowed. Default is 10.
min_confidence	Numeric vector of integer values between 0 and 10 indicating the precision of the returned result as defined by its geographical extent, (i.e. by the extent of the result's bounding box). See the <a href="#">API documentation</a> for details. Only results with at least the requested confidence will be returned. Default is NULL.
no_annotations	Logical vector indicating whether additional information about the result location should be returned. TRUE by default, which means that the results will not contain annotations.
no_dedupe	Logical vector (default FALSE), when TRUE the results will not be deduplicated.
no_record	Logical vector of length one (default FALSE), when TRUE no log entry of the query is created, and the geocoding request is not cached by OpenCage.
abbrv	Logical vector (default FALSE), when TRUE addresses in the formatted field of the results are abbreviated (e.g. "Main St." instead of "Main Street").
add_request	Logical vector (default FALSE) indicating whether the request is returned again with the results. If the return value is a <code>df_list</code> , the query text is added as a column to the results. <code>json_list</code> results will contain all request parameters, including the API key used! This is currently ignored by OpenCage if return value is <code>geojson_list</code> .

## Value

A list with

- results as a tibble with one line per result,
- the number of results as an integer,
- the timestamp as a POSIXct object,
- `rate_info` tibble/data.frame with the maximal number of API calls per day for the used key, the number of remaining calls for the day and the time at which the number of remaining calls will be reset.

## Examples

```
opencage_forward(placename = "Sarzeau")
opencage_forward(placename = "Islington, London")
```

```
opencage_forward(placename = "Triererstr 15,
                          Weimar 99423,
                          Deutschland")
```

---

opencage\_reverse      *Reverse geocoding*

---

## Description

### [Deprecated]

Deprecated: use `oc_reverse` or `oc_reverse_df` for reverse geocoding.

## Usage

```
opencage_reverse(
  latitude,
  longitude,
  key = opencage_key(),
  bounds = NULL,
  countrycode = NULL,
  language = NULL,
  limit = 10,
  min_confidence = NULL,
  no_annotations = FALSE,
  no_dedupe = FALSE,
  no_record = FALSE,
  abbrev = FALSE,
  add_request = TRUE
)
```

## Arguments

latitude, longitude	Numeric vectors of latitude and longitude values.
key	Your OpenCage API key as a character vector of length one. By default, <code>opencage_key()</code> will attempt to retrieve the key from the environment variable <code>OPENCAGE_KEY</code> .
bounds	Bounding box, ignored for reverse geocoding.
countrycode	Country code, ignored for reverse geocoding.
language	An <b>IETF BCP 47 language tag</b> (such as "es" for Spanish or "pt-BR" for Brazilian Portuguese). OpenCage will attempt to return results in that language. Alternatively you can specify the "native" tag, in which case OpenCage will attempt to return the response in the "official" language(s). In case the language parameter is set to <code>NULL</code> (which is the default), the tag is not recognized, or OpenCage does not have a record in that language, the results will be returned in English.
limit	How many results should be returned (1-100), ignored for reverse geocoding.

<code>min_confidence</code>	Numeric vector of integer values between 0 and 10 indicating the precision of the returned result as defined by its geographical extent, (i.e. by the extent of the result's bounding box). See the <a href="#">API documentation</a> for details. Only results with at least the requested confidence will be returned. Default is NULL.
<code>no_annotations</code>	Logical vector indicating whether additional information about the result location should be returned. TRUE by default, which means that the results will not contain annotations.
<code>no_dedupe</code>	Logical vector (default FALSE), when TRUE the results will not be deduplicated.
<code>no_record</code>	Logical vector of length one (default FALSE), when TRUE no log entry of the query is created, and the geocoding request is not cached by OpenCage.
<code>abbrv</code>	Logical vector (default FALSE), when TRUE addresses in the formatted field of the results are abbreviated (e.g. "Main St." instead of "Main Street").
<code>add_request</code>	Logical vector (default FALSE) indicating whether the request is returned again with the results. If the return value is a <code>df_list</code> , the query text is added as a column to the results. <code>json_list</code> results will contain all request parameters, including the API key used! This is currently ignored by OpenCage if return value is <code>geojson_list</code> .

## Value

A list with

- results as a tibble with one line per result,
- the number of results as an integer,
- the timestamp as a POSIXct object,
- `rate_info` tibble/data.frame with the maximal number of API calls per day for the used key, the number of remaining calls for the day and the time at which the number of remaining calls will be reset.

## Examples

```
opencage_reverse(  
  latitude = 0, longitude = 0,  
  limit = 2  
)
```

# Index

- \* **data**
  - countrycodes, [2](#)
  - .Renviron, [5](#), [6](#)
  - .Rprofile, [6](#)
- base::interactive(), [6](#)
- countrycodes, [2](#)
- oc\_bbox, [2](#)
- oc\_bbox(), [7](#), [11](#), [20](#)
- oc\_clear\_cache, [4](#)
- oc\_config, [5](#)
- oc\_config(), [5](#)
- oc\_forward, [6](#)
- oc\_forward(), [12](#), [16](#), [18](#)
- oc\_forward\_df, [9](#)
- oc\_forward\_df(), [8](#)
- oc\_points, [13](#)
- oc\_points(), [7](#), [11](#)
- oc\_reverse, [14](#)
- oc\_reverse(), [8](#), [12](#), [18](#)
- oc\_reverse\_df, [17](#)
- oc\_reverse\_df(), [8](#), [12](#), [16](#)
- opencage-deprecated, [19](#)
- opencage\_forward, [20](#)
- opencage\_forward(), [20](#)
- opencage\_key(), [20](#), [22](#)
- opencage\_reverse, [22](#)
- opencage\_reverse(), [20](#)
- option, [6](#)