

Package: tiler (via r-universe)

October 11, 2024

Title Create Geographic and Non-Geographic Map Tiles

Version 0.3.2

Description Creates geographic map tiles from geospatial map files or non-geographic map tiles from simple image files. This package provides a tile generator function for creating map tile sets for use with packages such as 'leaflet'. In addition to generating map tiles based on a common raster layer source, it also handles the non-geographic edge case, producing map tiles from arbitrary images. These map tiles, which have a non-geographic, simple coordinate reference system (CRS), can also be used with 'leaflet' when applying the simple CRS option. Map tiles can be created from an input file with any of the following extensions: tif, grd and nc for spatial maps and png, jpg and bmp for basic images. This package requires 'Python' and the 'gdal' library for 'Python'. 'Windows' users are recommended to install 'OSGeo4W' (<<https://trac.osgeo.org/osgeo4w/>>) as an easy way to obtain the required 'gdal' support for 'Python'.

License MIT + file LICENSE

URL <https://docs.ropensci.org/tiler/>,
<https://github.com/ropensci/tiler>

BugReports <https://github.com/ropensci/tiler/issues>

Imports png, raster, sp

Suggests bmp, jpeg, knitr, leaflet, parallel, rmarkdown, sf, testthat, webshot

VignetteBuilder knitr

ByteCompile true

Encoding UTF-8

LazyData true

Roxygen list(markdown = TRUE)

RoxygenNote 7.3.2

SystemRequirements Python (>= 2.7), python-gdal library (For Windows, gdal installed via OSGeo4W <<https://trac.osgeo.org/osgeo4w/>> recommended) clipboard

Repository <https://ropensci.r-universe.dev>

RemoteUrl <https://github.com/ropensci/tiler>

RemoteRef master

RemoteSha 2f43081405e32ffb4cf56962ed082919ac780639

Contents

tile	2
tiler	4
tiler-details	5
tiler_options	6
tile_viewer	7
view_tiles	8
Index	9

tile	<i>Create map tiles</i>
------	-------------------------

Description

Create geographic and non-geographic map tiles from a file.

Usage

```
tile(
  file,
  tiles,
  zoom,
  crs = NULL,
  resume = FALSE,
  viewer = TRUE,
  georef = TRUE,
  ...
)
```

Arguments

file	character, input file.
tiles	character, output directory for generated tiles.
zoom	character, zoom levels. Example format: "3-7". See details.

<code>crs</code>	character, Proj4 string. Use this to force set the CRS of a loaded raster object from <code>file</code> in cases where the CRS is missing but known, to avoid defaulting to non-geographic tiling.
<code>resume</code>	logical, only generate missing tiles.
<code>viewer</code>	logical, also create <code>preview.html</code> adjacent to <code>tiles</code> directory for previewing tiles in the browser using Leaflet.
<code>georef</code>	logical, for non-geographic tiles only. If <code>viewer = TRUE</code> , then the Leaflet widget in <code>preview.html</code> will add map markers with coordinate labels on mouse click to assist with georeferencing of non-geographic tiles.
<code>...</code>	additional arguments for projected maps: reprojection method or any arguments to <code>raster::RGB()</code> , e.g. <code>col</code> and <code>colNA</code> . See details. Other additional arguments <code>lng</code> and <code>lat</code> can also be passed to the tile previewer. See <code>tile_viewer()</code> for details.

Details

This function supports both geographic and non-geographic tile generation. When `file` is a simple image file such as `png`, `tile()` generates non-geographic, simple CRS tiles. Files that can be loaded by the `raster` package yield geographic tiles as long as `file` has projection information. If the raster object's Proj4 string is `NA`, it falls back on non-geographic tile generation and a warning is thrown.

Choice of appropriate zoom levels for non-geographic image files may depend on the size of the image. A zoom value may be partially ignored for image files under certain conditions. For instance using the example `map.png` below, when passing strictly `zoom = n` where `n` is less than 3, this still generates tiles for zoom `n` up through 3.

Supported file types: Supported simple CRS/non-geographic image file types include `png`, `jpg` and `bmp`. For projected map data, supported file types include three types readable by the `raster` package: `grd`, `tif`, and `nc` (requires `ncdf4`). Other currently unsupported file types passed to `file` throw an error.

Raster file inputs: If a map file loadable by `raster` is a single-layer raster object, tile coloring is applied. To override default coloring of data and `noData` pixels, pass the additional arguments `col` and `colNA` to `...`. Multi-layer raster objects are rejected with an error message. The only exception is a three- or four-band raster, which is assumed to represent red, green, blue and alpha channels, respectively. In this case, processing will continue but coloring arguments are ignored as unnecessary.

Prior to tiling, a geographically-projected raster layer is reprojected to EPSG:4326 only if it has some other projection. The only reprojection argument available through `...` is `method`, which can be "bilinear" (default) or "ngb". If complete control over reprojection is required, this should be done prior to passing the rasterized file to the `tile` function. Then no reprojection is performed by `tile()`. When `file` consists of RGB or RGBA bands, `method` is ignored if provided and reprojection uses nearest neighbor.

It is recommended to avoid using a projected 4-band RGBA raster file. However, the alpha channel appears to be ignored anyway. `gdal2tiles` gives an internal warning. Instead, create

your RGBA raster file in unprojected form and it should pass through to `gdal2tiles` without any issues. Three-band RGB raster files are unaffected by reprojection.

Tiles and Leaflet: `gdal2tiles` generates TMS tiles. If expecting XYZ, for example when using with Leaflet, you can change the end of the URL to your hosted tiles from `{z}/{x}/{y}.png` to `{z}/{x}/{-y}.png`.

This function is supported by two different versions of `gdal2tiles`. There is the standard version, which generates geospatial tiles in TMS format. The other version of `gdal2tiles` handles basic image files like a `magick` package documentation for working with custom tiles in Leaflet.

Value

nothing is returned but tiles are written to disk.

See Also

[view_tiles\(\)](#), [tile_viewer\(\)](#)

Examples

```
# non-geographic/simple CRS
x <- system.file("maps/map.png", package = "tiler")
tiles <- file.path(tempdir(), "tiles")
tile(x, tiles, "2-3")

## Not run:
# unprojected map
x <- system.file("maps/map_wgs84.tif", package = "tiler")
tile(x, tiles, 0)

# projected map
x <- system.file("maps/map_albers.tif", package = "tiler")
tile(x, tiles, 0)

## End(Not run)
```

tiler

tiler: Create Geographic and Non-Geographic Map Tiles

Description

Creates geographic map tiles from geospatial map files or non-geographic map tiles from simple image files. This package provides a tile generator function for creating map tile sets for use with packages such as 'leaflet'. In addition to generating map tiles based on a common raster layer source, it also handles the non-geographic edge case, producing map tiles from arbitrary images. These map tiles, which have a non-geographic, simple coordinate reference system (CRS), can also be used with 'leaflet' when applying the simple CRS option. Map tiles can be created from an input

file with any of the following extensions: tif, grd and nc for spatial maps and png, jpg and bmp for basic images. This package requires 'Python' and the 'gdal' library for 'Python'. 'Windows' users are recommended to install 'OSGeo4W' (<https://trac.osgeo.org/osgeo4w/>) as an easy way to obtain the required 'gdal' support for 'Python'.

Author(s)

Maintainer: Matthew Leonawicz <rpkgs@pm.me> ([ORCID](#))

Other contributors:

- Alex M Chubaty <achubaty@for-cast.ca> ([ORCID](#)) [contributor]

See Also

Useful links:

- <https://docs.ropensci.org/tiler/>
- <https://github.com/ropensci/tiler>
- Report bugs at <https://github.com/ropensci/tiler/issues>

tiler-details

tiler: Create Map Tiles from R

Description

The tiler package creates geographic map tiles from geospatial map files or non-geographic map tiles from simple image files.

Details

This package provides a tile generator function for creating map tile sets for use with packages such as leaflet. In addition to generating map tiles based on a common raster layer source, it also handles the non-geographic edge case, producing map tiles from arbitrary images. These map tiles, which have a non-geographic simple coordinate reference system (CRS), can also be used with leaflet when applying the simple CRS option.

Map tiles can be created from an input file with any of the following extensions: tif, grd and nc for spatial maps and png, jpg and bmp for basic images.

This package requires Python and the gdal library for Python. Windows users are recommended to install OSGeo4W: <https://trac.osgeo.org/osgeo4w/> as an easy way to obtain the required gdal support for Python in Windows.

tiler_options	<i>Options</i>
---------------	----------------

Description

Options for tiler package.

Usage

```
tiler_options(...)
```

Arguments

... a list of options.

Details

On Windows systems, if the system paths for `python.exe` and `OSGeo4W.bat` are not added to the system PATH variable, they must be provided by the user after loading the package. It is recommended to add these to the system path so they do not need to be specified for every R session.

As long as you are using `OSGeo4W`, you can ignore the Python path specification and do not even need to install it on your system separately; `OSGeo4W` will use its own built-in version.

The recommended way to have GDAL available to Python in Windows is to install `OSGeo4W`. This is commonly installed along with `QGIS`.

By default, `tiler_options()` is set on package load with `osgeo4w = "OSGeo4W.bat"`. It is expected that the user has added the path to this file to the system PATH variable in Windows. For example, if it is installed to `C:/OSGeo4W64/OSGeo4W.bat`, add `C:/OSGeo4W64` to your PATH. If you do want to specify the path in the R session using `tiler_options()`, provide the full path including the filename. See the example.

None of this applies to other systems. As long as the system requirements, Python and GDAL, are installed, then `tile()` should generate tiles without getting or setting any `tiler_options()`.

Value

The function prints all set options if called with no arguments. When setting options, nothing is returned.

Examples

```
tiler_options()
tiler_options(osgeo4w = "C:/OSGeo4W64/OSGeo4W.bat")
```

`tile_viewer`*Create an HTML tile preview*

Description

Create an HTML file that displays a tile preview using Leaflet.

Usage

```
tile_viewer(tiles, zoom, width = NULL, height = NULL, georef = TRUE, ...)
```

Arguments

<code>tiles</code>	character, directory where tiles are stored.
<code>zoom</code>	character, zoom levels full range. Example format: "3-7".
<code>width</code>	NULL (default) for geospatial map tiles. The original image width in pixels for non-geographic, simple CRS tiles.
<code>height</code>	NULL (default) for geospatial map tiles. The original image height in pixels for non-geographic, simple CRS tiles.
<code>georef</code>	logical, for non-geographic tiles only. If <code>viewer = TRUE</code> , then the Leaflet widget in <code>preview.html</code> will add map markers with coordinate labels on mouse click to assist with georeferencing of non-geographic tiles.
<code>...</code>	additional optional arguments include <code>lng</code> and <code>lat</code> for setting the view longitude and latitude. These three arguments only apply to geographic tiles. Viewer centering is $(0, 0)$ by default.

Details

This function creates a file `preview.html` adjacent to the `tiles` base directory. When loaded in the browser, this file displays map tiles from the adjacent folder. For example, if tiles are stored in `project/tiles`, this function creates `project/preview.html`.

By default, `tile()` creates this file. The only reasons to call `tile_viewer()` directly after producing map tiles are: (1) if `viewer = FALSE` was set in the call to `tile()`, (2) if `tile()` was called multiple times, e.g., for different batches of zoom levels, and thus the most recent call did not use the full zoom range, or (3) `preview.html` was deleted for some other reason.

If calling this function directly, ensure that the min and max zoom, and original image pixel dimensions if applicable, match the generated tiles. These arguments are passed to `tile_viewer` automatically when called w

Value

nothing is returned, but a file is written to disk.

See Also

[view_tiles\(\)](#), [tile\(\)](#)

Examples

```
tile_viewer(file.path(tempdir(), "tiles"), "3-7") # requires existing tiles
```

`view_tiles`*View map tiles with Leaflet*

Description

View map tiles in the browser using leaflet.

Usage

```
view_tiles(tiles)
```

Arguments

`tiles` character, directory where tiles are stored.

Details

This function opens `preview.html` in a web browser. This file displays map tiles in a Leaflet widget. The file is created when `tile()` is called to generate the map tiles, unless `viewer = FALSE`. Alternatively, it is created (or re-created) subsequent to tile creation using `tile_viewer()`.

Value

nothing is returned, but the default browser is launched.

See Also

[tile_viewer\(\)](#), [tile\(\)](#)

Examples

```
# launches browser; requires an existing tile set
## Not run: view_tiles(file.path(tempdir(), "tiles"))
```

Index

tile, 2
tile(), 7, 8
tile_viewer, 7
tile_viewer(), 3, 4, 8
tiler, 4
tiler-details, 5
tiler-package (tiler), 4
tiler_options, 6

view_tiles, 8
view_tiles(), 4, 7